

VPMR v.7

DLL Reference Manual

August 16



Initialization / Finalization	4
<i>vpmrInit</i>	4
<i>vpmrEnd</i>	6
<i>vpmrAddCountry</i>	7
Reading Plates	8
<i>vpmrRead</i>	8
<i>vpmrReadRGB24</i>	9
<i>vpmrReadRGB32</i>	10
<i>vpmrReadBMP</i>	11
<i>vpmrReadJPG</i>	12
Retrieving Results	13
<i>vpmrGetNumberOfPlates</i>	13
<i>vpmrGetText</i>	14
<i>vpmrGetNumberOfCharacters</i>	15
<i>vpmrGetPolarity</i>	16
<i>vpmrGetGlobalConfidence</i>	17
<i>vpmrGetAverageCharacterHeight</i>	18
<i>vpmrGetCharacterConfidence</i>	19
<i>vpmrGetRectangle</i>	20
<i>vpmrGetFormat</i>	21
<i>vpmrGetCharRectangle</i>	22
Time Management	23
<i>vpmrGetProcessingTime</i>	23
<i>vpmrSetTimeOut</i>	24
Optional Configuration	25
<i>vpmrSetCorrectionCoefficients</i>	25
<i>vpmrSetCorrectionCoefficientsEx</i>	26
<i>vpmrSetDistortionCorrectionOff</i>	27
<i>vpmrConfigureAutomaticCharacterHeight</i>	28
<i>vpmrSetRectangle</i>	29
<i>vpmrShadowKillerOn</i>	30
<i>vpmrShadowKillerOff</i>	31
<i>vpmrStrictSyntaxOn</i>	32
<i>vpmrStrictSyntaxOff</i>	33
<i>vpmrSetScaleFactor</i>	34
<i>vpmrReturnSpaces</i>	35

	36
<i>vpmrWriteHASP</i>	36
<i>vpmrReadHASP</i>	37
Example of Use	38

Initialization / Finalization

vpmrInit

Initializes the **Vehicle Plates Automatic Reader (VPAR)**. It loads the Artificial Neural Networks used by the OCR and initializes parameters. This function must be called before calling any other function in this library.

```
long vpmrInit ( char* PathToMap,
                long ICountryCode,
                long IAverageCharacterHeight,
                bool bDuplicateLines,
                bool Ireserved1,
                long Ireserved2,
                bool bTrace = false );
```

Arguments

<i>PathToMap</i>	Path to folders that contains map files
<i>ICountryCode</i>	County code used for selecting the target country for license plate recognition. See declaration file for a list of supported countries.
<i>IAvCharacterHeight</i>	Approximate average height of the characters in the plates to read. If this argument is -1 , the library uses <i>automatic height mode</i> and tries to read characters of any height. If -1 is passed, the processing time will be increased.
<i>bDuplicateLines</i>	In order to properly recognize images acquired with only half of the scan lines, this argument must be true . For images acquired with all the lines, this parameter must be false .
<i>Ireserved1</i>	Sort characters in squared plates (plates with two rows of characters). If this argument is false , the characters in the top row are returned first, followed by the characters in the bottom row. If it is true , the characters are re-arranged to match the Spanish format. (For example, if this parameter is true , a plate with the top line "BU AX" and bottom line "5278" would be re-arranged to generate the result "BU5278AX". In the other hand, if this argument is false , the result would be "BUAX5278").

lreserved2 Activate special filter for colour treatment. Possible values are:

- 0 Average value of the three channels (**Recommended, default value**)
- 1 Use first colour channel (red for RGB image or blue in case of BGR)
- 2 Use second colour channel (green always)
- 3 Use the third colour channel (blue for RGB image, red for BGR image)
- < 0 Error
- > 3 Error

bTrace This parameter must be set to **false**.

Return Value

- 0** → Error.
- 1** → Ok.

vpmrEnd

Frees the memory allocated by the **Vehicle Plates Automatic Reader (VPMR)**. Only call this function at the end of the program.

```
void vpmrEnd ( void );
```

vpmrAddCountry

This feature should only be used when the library is initialized in multicountry (**code 100**) mode. In this case, AddCountry is used to add countries to consider for reading. Initially (after the Init), no country is included and must be called at least once.

```
long vpmrAddCountry ( long ICountryCode);
```

Parámetros

ICountryCode Country code.

Return Value

0 → Error.

1 → Ok.

vpmrRead

This function reads the license plate present within an image. The input to this function is an image. It analyzes the image looking for a vehicle plate and if it finds it, it reads the plate. A set of functions is supplied to retrieve the result of the recognition (see *Retrieving Results* chapter below).

The input supplied to this function is the *image buffer* in **256 grayscale** levels (1 byte per pixel). The *width* and *height* of the image must be supplied as well.

```
long vpmrRead ( long lWidth,  
                long lHeight,  
                unsigned char * pbImageData );
```

Arguments

<i>lWidth</i>	Width (in pixels) of the image that will be analyzed.
<i>lHeight</i>	Height (in pixels) of the image that will be analyzed.
<i>pbImageData</i>	Buffer with the image data (pixels), in 256 grey levels (1 byte per pixel).

Return Value

- 0** → Error.
- 1** → Ok.

vpmrReadRGB24

This function reads the vehicle plate present within an image. The input to this function is an image. It analyzes the image looking for a vehicle plate and if it finds it, it reads the plate. A set of functions is supplied to retrieve the result of the recognition (see *Retrieving Results* chapter below).

The input supplied to this function is the *image buffer* in **RGB-24 bits** (3 bytes per pixel) format. The *width* and *height* of the image must be supplied as well.

```
long vpmrReadRGB24 ( long lWidth,  
                    long lHeight,  
                    unsigned char * pbImageData,  
                    bool bFlip = false );
```

Arguments

<i>lWidth</i>	Width (in pixels) of the image that will be analyzed.
<i>lHeight</i>	Height (in pixels) of the image that will be analyzed.
<i>pbImageData</i>	<i>Buffer</i> with the image data (pixels) using 3 bytes per pixel (RED, GREEN, BLUE).
<i>bFlip</i>	This value must be true only if the RGB buffer contains first the bottom row of the image, then the next one upwards, and so on. The last line of values in the buffer contains the top row of pixels in the image. Some devices acquire the RGB buffer in this way (<i>bottom-up</i>).

Return Value

- 0** → Error.
- 1** → Ok.

vpmrReadRGB32

This function reads the vehicle plate present within an image. The input to this function is an image. It analyzes the image looking for a vehicle plate and if it finds it, it reads the plate. A set of functions is supplied to retrieve the result of the recognition (see *Retrieving Results* chapter below).

The input supplied to this function is the *image buffer* in **RGB-32 bits** (4 bytes per pixel) format. The *width* and *height* of the image must be supplied as well.

```
long vpmrReadRGB32 ( long IWidth,  
                    long IHeight,  
                    unsigned char * pbImageData,  
                    bool bFlip = false );
```

Arguments

<i>IWidth</i>	Width (in pixels) of the image that will be analyzed.
<i>IHeight</i>	Height (in pixels) of the image that will be analyzed.
<i>pbImageData</i>	<i>Buffer</i> with the image data (pixels) using 4 bytes per pixel (RED, GREEN, BLUE, ALPHA).
<i>bFlip</i>	This value must be true only if the RGB buffer contains first the bottom row of the image, then the next one upwards, and so on. The last line of values in the buffer contains the top row of pixels in the image. Some devices acquire the RGB buffer in this way (<i>bottom-up</i>).

Return Value

0 → Error.
1 → Ok.

vpmrReadBMP

This function reads the vehicle plate present within an image. The input to this function is an image. It analyzes the image looking for a vehicle plate and if it finds it, it reads the plate. A set of functions is supplied to retrieve the result of the recognition (see *Retrieving Results* chapter below).

The input supplied to this function is an image file in standard Bitmap (BMP) format.

```
long vpmrReadBMP ( char * strFilename );
```

Arguments

<i>strFilename</i>	Filename of BMP image to process.
--------------------	-----------------------------------

Return Value

0 → Error.
1 → Ok.

vpmrReadJPG

This function reads the vehicle plate present within an image. The input to this function is an image. It analyzes the image looking for a vehicle plate and if it finds it, it reads the plate. A set of functions is supplied to retrieve the result of the recognition (see *Retrieving Results* chapter below).

The input supplied to this function is an image file in standard Jpeg (JPG) format.

```
long vpmrReadJPG ( char * strFilename );
```

Arguments

<i>strFilename</i>	Filename of JPG image to process.
--------------------	-----------------------------------

Return Value

0 → Error.
1 → Ok.

Retrieving Results

vpmrGetNumberOfPlates

Returns the number of plates found and recognized in the last analyzed image.

```
long vpmrGetNumberOfPlates ( void );
```

Return Value

Returns the number of vehicle plates read.

Remarks

This value will be **0** if no vehicle plate is found or if it cannot be read. It will be **1** if one vehicle plate was found and recognized and **2** only if **vpmrInit** was called with the argument *bTrailersOn* set to **true** and the processed image contains the two plates at the back of a truck carrying a trailer.

vpmrGetText

Returns the text (in **ASCII** format) of the vehicle plate read in the last processed image.

```
long vpmrGetText ( char * strResult,  
                  long lPlate = 0 );
```

Arguments

strResult String where the ASCII text is returned.

lPlate Index of the plate we want to retrieve.
If only one plate was read, number **0** must be specified.
If two plates were read (a truck with two plates at the back), the
result for plate number **0** or number **1** can be requested.

Return Value

0 → Error.

1 → Ok.

vpmrGetNumberOfCharacters

Returns the number of characters present in the last plate processed by **VPAR**.

```
long vpmrGetNumberOfCharacters ( long lPlate = 0 );
```

Arguments

<i>lPlate</i>	Index of the plate we want to retrieve. If only one plate was read, number 0 must be specified. If two plates were read (a truck with two plates at the back), the result for plate number 0 or number 1 can be requested.
---------------	---

Return Value

Number of recognized characters.

vpmrGetPolarity

Returns the polarity of the plate.

```
long vpmrGetPolarity ( long lPlate = 0 );
```

Arguments

<i>lPlate</i>	Index of the plate we want to retrieve. If only one plate was read, number 0 must be specified. If two plates were read (a truck with two plates at the back), the result for plate number 0 or number 1 can be requested.
---------------	---

Return Value

Polarity of the plate: 1 for dark chars on bright background, 2 otherwise.

vpmrGetGlobalConfidence

Returns a confidence factor for the result of the last plate recognized by the **Vehicle Plates Automatic Reader**.

This value is expressed as a percentage (0% – 100%).

```
float vpmrGetGlobalConfidence ( long lPlate = 0 );
```

Arguments

<i>lPlate</i>	Index of the plate we want to retrieve. If only one plate was read, number 0 must be specified. If two plates were read (a truck with two plates at the back), the result for plate number 0 or number 1 can be requested.
---------------	---

Return Value

The Confidence Factor for the last recognition.

vpmrGetAverageCharacterHeight

Returns the average height (in pixels) of the characters present in the last plate recognized by the **Vehicle Plates Automatic Reader**.

```
float vpmrGetAverageCharacterHeight ( long lPlate = 0 );
```

Arguments

<i>lPlate</i>	Index of the plate we want to retrieve. If only one plate was read, number 0 must be specified. If two plates were read (a truck with two plates at the back), the result for plate number 0 or number 1 can be requested.
---------------	---

Return Value

The average height (in pixels) of the characters in the last plate analyzed.

vpmrGetCharacterConfidence

Returns a confidence factor for a given character within the last plate analyzed.

This value is expressed as a percentage (0% – 100%).

```
float vpmrGetCharacterConfidence ( long lIndex ,  
                                   long lPlate = 0 );
```

Arguments

lIndex (0..n) Index of the character we want to retrieve the confidence factor for.

lPlate Index of the plate we want to retrieve.
If only one plate was read, number **0** must be specified.
If two plates were read (a truck with two plates at the back), the result for plate number **0** or number **1** can be requested.

Return Value

Character Confidence Factor.

vpmrGetRectangle

Returns the coordinates of the rectangle containing the vehicle license plate in the last image processed.

```
void vpmrGetRectangle ( long * pLeft,  
                        long * pTop,  
                        long * pRight,  
                        long * pBottom,  
                        long lPlate = 0 );
```

Arguments

<i>pLeft</i>	X-Coordinate of the Upper-Left corner of the rectangle.
<i>pTop</i>	Y-Coordinate of the Upper-Left corner of the rectangle.
<i>pRight</i>	X-Coordinate of the Lower-Right corner of the rectangle.
<i>pBottom</i>	Y-Coordinate of the Lower-Right corner of the rectangle.
<i>lPlate</i>	Index of the plate we want to retrieve. If only one plate was read, number 0 must be specified. If two plates were read (a truck with two plates at the back), the result for plate number 0 or number 1 can be requested.

vpmrGetFormat

This property returns the country code that matches license plate result. Example: If the software detects reading of a Spanish license plate, code returned is 101. If no country is detected it returns 0. For European license plates (no country detected) it returns 100.

```
long vpmrGetFormat ( long lPlate);
```

Parameters

lPlate Number of license plate read result to query about (0 to 7).

Return value

- 0** → No license plate format detected.
- N** → Country code or continent of detected format.

vpmrGetCharRectangle

Returns the coordinates of the rectangle containing a given character in the last plate analyzed. **The coordinates are relatives to saved image by vpmrSavePlateImage function.**

```
void vpmrGetRectangle (long lIndex,  
                      long * plLeft,  
                      long * plTop,  
                      long * plRight,  
                      long * plBottom,  
                      long lPlate = 0 );
```

Parameters

<i>lIndex</i>	Index of the character (first character has index = 0).
<i>plLeft</i>	X-Coordinate of the Upper-Left corner of the rectangle.
<i>plTop</i>	Y-Coordinate of the Upper-Left corner of the rectangle.
<i>plRight</i>	X-Coordinate of the Lower-Right corner of the rectangle.
<i>plBottom</i>	Y-Coordinate of the Lower-Right corner of the rectangle.
<i>lPlate</i>	If there is more than one plate found, this is the plate index (0 for the first one)

Time Management

vpmrGetProcessingTime

Returns the processing time for the last reading operation.

This value is expressed in milliseconds.

```
long vpmrGetProcessingTime ( );
```

Return Value

Processing time (in milliseconds) for the last reading.

vpmrSetTimeOut

This function specifies the maximum processing time for reading operations.

This value is expressed in milliseconds.

```
void vpmrSetTimeOut ( long lMilliseconds );
```

Arguments

<i>lMilliseconds</i>	Maximum processing time (in milliseconds).
----------------------	--

Remarks

This maximum time is approximate. This means that the actual processing time can be (in some cases) slightly longer than the time-out specified.

Optional Configuration

vpmrSetCorrectionCoefficients

This function sets the distortion correction coefficients that will be applied to all the images before being analyzed.

The types of distortions that can be corrected are: tangential distortion (horizontal and/or vertical perspective) and rotation.

The specified coefficients will be applied to all the images until this function is called again with different arguments of **vpmrSetDistortionCorrectionOff** is called.

```
void vmrSetCorrectionCoefficients (    float fDistance,  
                                     float fVerticalCoeff,  
                                     float fHorizontalCoeff,  
                                     float fAngle);
```

Arguments

<i>fDistance</i>	Approximate distance between camera and object (in meters).
<i>fVerticalCoeff</i>	Coefficient for correcting Vertical Perspective.
<i>fHorizontalCoeff</i>	Coefficient for correcting Horizontal Perspective.
<i>fAngle</i>	Angle for correcting Rotation.

vpmrSetCorrectionCoefficientsEx

This function sets the distortion correction coefficients that will be applied to all the images before being analyzed.

The types of distortions that can be corrected are: tangential distortion (horizontal and/or vertical perspective) and rotation.

The specified coefficients will be applied to all the images until this function is called again with different arguments of **vpmrSetDistortionCorrectionOff** is called.

```
void vpmrSetCorrectionCoefficients (
    float fDistance,
    float fVerticalCoeff,
    float fHorizontalCoeff,
    float fAngle,
    float fVerticalSkew,
    float fHorizontalSkew
);
```

Arguments

<i>fDistance</i>	Approximate distance between camera and object (in meters).
<i>fVerticalCoeff</i>	Coefficient for correcting Vertical Perspective.
<i>fHorizontalCoeff</i>	Coefficient for correcting Horizontal Perspective.
<i>fAngle</i>	Angle for correcting Rotation.
<i>fVerticalSkew</i>	Coefficient for correcting Vertical Skew.
<i>fHorizontalSkew</i>	Coefficient for correcting Horizontal Skew.

vpmrSetDistortionCorrectionOff

This function deactivates the distortion correction pre-process.

Use **vpmrSetCorrectionCoefficients** to activate it again.

```
void vpmrSetDistortionCorrectionOff ();
```

vpmrConfigureAutomaticCharacterHeight

This function configures the Automatic Character Height steps.

When **vpmrInit** is called with the argument *IAvCharacterHeight* set to -1, the automatic character height mode is selected. By default, the range of character heights scanned in this mode is from 25 pixels to 60 pixels.

By using this function, the user can select the heights that VPMR will scan.

```
long vpmrConfigureAutomaticCharacterHeight (    long INumSteps,  
                                              long * pISteps );
```

Arguments

INumSteps Always 2.

pISteps Array with the start of the interval in the first position and the end of the interval in second position, e.g. 25, 45

Return Value

0 → Error.

1 → Ok.

Remarks

To recover the default configuration, the following code must be executed:

```
long ISteps[2] = { 25, 60 };  
vpmrConfigureAutomaticCharacterHeight (2, ISteps );
```

vpmrSetRectangle

Sets the rectangle within the image where the inspection process will take place. Only the provided region will be inspected to look for a license plate.

This function can be used to speed up the process when the approximate position of the license plate within the image is known.

```
long vpmrSetRectangle (    long ILeft,  
                           long ITop,  
                           long IWidth,  
                           long IHeight );
```

Arguments

ILeft, ITop Left-top corner coordinates of the rectangle (in *píxels*).

IWidth, IHeight Rectangle dimensions (in *píxels*).

Return Value

0 → Error.

1 → Ok.

Remarks

The inspection rectangle specified will be applied to all the further inspections until *vpmrSetRectangle* is called again with different parameters.

In order to inspect the whole image, *vpmrSetRectangle* must be called with all its parameters set to 0:

```
vpmrSetRectangle (0, 0, 0, 0);
```

By default, after library initialization with *vpmrInit*, the inspection rectangle is set to inspect the whole image.

vpmrShadowKillerOn

Activates the pre-processing for dealing with shadows cast on the upper side of the plates.

```
void vpmrShadowKillerOn ();
```

vpmrShadowKillerOff

Deactivates the pre-processing for dealing with shadows cast on the upper side of the plates.

```
void vpmrShadowKillerOff ();
```

vpmrStrictSyntaxOn

By calling this function, the format returned for custom plates (plates not following the standard country's syntax) is 0.

```
void vpmrStrictSyntaxOn ();
```


vpmrStrictSyntaxOff

By calling this function, the format returned for custom plates (plates not following the standard country's syntax) is the country's format (this is the default mode).

```
void vpmrStrictSyntaxOff ();
```

vpmrSetScaleFactor

Scales the image internally before processing it.

```
void vpmrSetScaleFactor ( float fScale );
```

Arguments

<i>fScale</i>	Scale factor. Width and height dimensions of the input image are multiplied by this factor.
---------------	---

Remark: The scaling takes place internally and therefore the configuration parameters (character height, rectangle of interest, etc...) must relate to the original image.

The results (average character height, rectangle, etc...) also relate to the original dimensions of the image.

vpmrReturnSpaces

By calling this function after vpmrInit the number plates recognized will be returned including the spaces between characters.

```
void vpmrReturnSpaces ();
```

Storing Data into the HASP Dongle

vpmrWriteHASP

Writes data into the internal memory of the HASP dongle. This capability for storing data into the HASP can be used for any purpose. Data is encrypted automatically before being written into the HASP memory.

A maximum of 24 bytes can be written.

```
long vpmrWriteHASP ( unsigned char * pData,  
                    long lSize );
```

Arguments

<i>pData</i>	Buffer containing the data to be written in to the HASP internal memory.
<i>lSize</i>	Size (in bytes) of the data to write (maximum 24 bytes).

Return Value

0 → Error.
1 → Ok.

vpmrReadHASP

Reads the data stored in the internal memory of the HASP dongle. Data is automatically decrypted after being read from the HASP memory.

```
long vpmrReadHASP ( unsigned char * pData,  
                    long lSize );
```

Arguments

pData Buffer where the retrieved data will be stored.

lSize Size (in bytes) of the data to read.

Return Value

0 → Error.

1 → Ok.

Example of Use

```
void func ()
{
    bool ok;
    // The characters in the images to process have about 30 pixels in height,
    // there is no need to duplicate horizontal lines (all the scan lines are acquired)
    // and we want two-lines plates to be re-arranged to fit the spanish format.
    ok = (bool) vpmrInit (PATH,_CODE_ITA,30, false, true, 0, false);
    if (ok)
    {
        unsigned char * buffer; // Image buffer.
        long numchars; // Number of characters read.
        char text[32]; // String where the result will be stored.
        float Cf; // Confidence Factor of the reading result.
        float characterCf[32]; // Array to store the characters confidence factor.
        // Buffer memory allocation.
        ...
        // Acquire the image buffer in 256 grayscale levels (1 byte per pixel) and store it
        // into buffer.
        ...
        // Image dimensions are 384x288 pixels.
        ok = (bool) vpmrRead (384, 288, buffer);
        if (ok)
        {
            vpmrGetText (text, 0);
            Cf = vpmrGetGlobalConfidence (0);
            numchars = vpmrGetNumberOfCharacters (0);
            for (long i = 0; i < numchars; i++)
            {
                characterCf[i] = vpmrGetCharacterConfidence (i, 0);
            }
        }
        else
        {
            // Error reading license plate.
        }

        // Read more images.
        ...
        // Finalize the software

        vpmrEnd ();
    }
    else
    {
        // Error initializing the VPMR.
    }
}
```